Adiabatic Expansion ($\Delta Q = 0$)


Occurs if:

- change is made sufficiently quickly
- and/or with good thermal isolation.

Governing formula:


$$PV^{\gamma}$$
 = constant

where $\gamma = C_P / C_V$



Because PV/T is constant (ideal gas):

 $V^{\gamma-1}T$ = constant (for adiabatic)



Rearrange:

 $(dP/P) = - (C_V + R)/C_V (dV/V)$ = - $\gamma (dV/V)$

where $\gamma = (C_V + R)/C_V = C_P/C_V$

Integrate both sides:

 $ln(P) = -\gamma ln(V) + constant$

or

 $ln(PV^{\gamma}) = constant$

or

 PV^{γ} = constant

QED

Irreversible Processes

Examples:

- Block sliding on table comes to rest due to friction: KE converted to heat.
- Heat flows from hot object to cold object.
- Air flows into an evacuated chamber.

Reverse process allowed by energy conservation, yet it does not occur.




Why?

2nd Law of Thermodynamics (entropy)

<u>Heat Engines</u>

Heat engine: a <u>cyclic</u> device designed to convert heat into work.



2nd Law of TD (Kelvin form):

It is impossible for a cyclic process to remove thermal energy from a system at a single temperature and convert it to mechanical work without changing the system or surroundings in some other way. For a cyclic engine $\Delta U = 0$,

So work done is equal to heat in minus heat out:

 $W = Q_H - Q_C$

Define the Efficiency of the engine:


 $\varepsilon = W/Q_H = (Q_H - Q_C)/Q_H = 1 - Q_C/Q_H$

Corollary of the 2nd Law of TD:

It is impossible to make a heat engine whose efficiency is 100%.

Refrigerators

Refrigerator: a cyclic device which uses work to transfer heat from a cold reservoir to hot reservoir.



2nd Law of TD (Clausius form):

It is impossible for a cyclic process to have no other effect than to transfer thermal energy from a cold object to a hot object. A measure of refrigerator performance is the ratio:

 $K = Q_c / W$

"Coefficient of performance" (The larger the better.)


Corollary of the 2nd Law of TD:

It is impossible for the coefficient of performance to be infinite.

<u>Equivalence of Kelvin and</u> <u>Clausius</u> Statements

For example:

You could combine an ordinary refrigerator with a <u>perfect</u> engine (impossible)...



to obtain a <u>perfect</u> refrigerator (also impossible).

The Carnot Engine

2nd Law of TD says:

100% efficient Heat Engine is impossible.


What is the maximum possible efficiency?

No engine working between 2 heat reservoirs can be more efficient than an <u>ideal</u> engine acting in a Carnot cycle. (Sadi Carnot, 1824)

Properties of the Carnot cycle:

- 1. It is reversible: no friction or other dissipative forces.
- 2. Heat conduction only occurs isothermally at the temperatures of the two reservoirs.

Derivation of Carnot Efficiency




- 1-2: Isothermal (Q_{in} at T_H)
- 2-3: Adiabatic expansion
- 3-4: Isothermal (Q_{out} at T_C)
- 4-1: Adiabatic compression

$$\varepsilon = 1 - T_C / T_H$$

The Stirling Engine

Invented by Robert Stirling in 1816. Its operating cycle is:



The two temperature-changing steps are performed at constant volume; A heat transfer occurs at these steps also.

Entropy

Consider a reversible process for an ideal gas:

 $dQ = dU + dW = n C_V dT + P dV$

 $= n C_V dT + n R T (dV/V)$

We cannot write a general integral of this, because dW (and therefore dQ) depends on the functional form of T(V) (i.e. the path). However, if we divide by T:

 $dQ/T = n C_V (dT/T) + n R (dV/V)$


is integrable independent of path.

```
This suggests a new state function,

<u>Entropy</u>, defined by:

\Delta S = S_f - S_i = \int_i^f \frac{dQ}{T}
(Valid for any system)
```

In general, the process may be too complicated to do the integral (particularly if irreversible process):



However, because entropy is a state function, we can choose any convenient path between i and f to integrate.

For an ideal gas:

```
\Delta S = n C_V \ln(T_f/T_i) + n R \ln(V_f/V_i)
```

This only depends on the initial state (V_i, T_i) and final state (V_f, T_f) , but not the path.

<u>Isothermal Expansion</u>: $T_f = T_i, V_f > V_i$

The amount of heat which leaves the reservoir and enters the gas is

 $Q = n R T ln(V_f/V_i).$

The entropy change of the gas is

 $\Delta S_{gas} = + Q/T = n R \ln(V_f/V_i).$

The entropy change of the reservoir is

 $\Delta S_{reservoir} = -Q/T.$

The net entropy change is


 $\Delta S_{universe} = \Delta S_{gas} + \Delta S_{reservoir} = 0.$

This illustrates a general result:


In a reversible process, the entropy change of the universe (system + surroundings) is zero.

Adiabatic Free Expansion of an Ideal Gas


Two containers connected by stopcock. They are thermally insulated so no heat can flow in or out.



<u>Initial</u>: One container is evacuated. Gas is in volume V_i at temperature T_i



<u>Final</u>: Stopcock opened, gas rushes into second chamber. Gas does no work (nothing to push against) and there is no heat transfer. So internal energy does not change. Final volume $V_f > V_i$ at temperature $T_f = T_i$. Because there is no heat transfer, you might think $\Delta S = 0$. WRONG! This is an irreversible process. We can't integrate



But entropy is a state function, and we do know the initial and final conditions for the Free Expansion. They are exactly the same as for an Isothermal Expansion. So

$\Delta S_{gas} = n R \ln(V_f/V_i).$

just as for an isothermal expansion. However, since it is thermally isolated from its surroundings,

 $\Delta S_{surround} = 0$ and $\Delta S_{universe} = \Delta S_{gas} + \Delta S_{surround} = n R \ln(V_f/V_i)$ > 0.


In an irreversible process, the entropy of the universe increases.

Entropy and Heat Engines

For a reversible cycle:



This implies that dQ cannot be strictly positive. There must also be heat released in the cycle.



Carnot cycle: $(Q_{in}/T_H) + (-Q_{out}/T_C) = 0.$

 2^{nd} Law of TD (Entropy form): $\Delta S_{universe} \ge 0.$ (greater-than sign for irreversible processes, and equals sign for reversible processes)

Entropy and Probability

(A statistical view)

Entropy ~ a measure of the disorder of a system.

A state of high order = low probability A state of low order = high probability

In an irreversible process, the universe moves from a state of low probability to a state of higher probability.

We will illustrate the concepts by considering the free expansion of a gas from volume V_i to volume V_f .


The gas always expands to fill the available space. It never spontaneously compresses itself back into the original volume. First, two definitions:

Microstate: a description of a system that specifies the properties (position and/or momentum, etc.) of each individual particle.

Macrostate: a more generalized description of the system; it can be in terms of macroscopic quantities, such as P and V, or it can be in terms of the number of particles whose properties fall within a given range.

In general, each macrostate contains a large number of microstates.

<u>An example</u>: Imagine a gas consisting of just 2 molecules. We want to consider whether the molecules are in the left or right half of the container.



There are 3 macrostates: both molecules on the left, both on the right, and one on each side. There are 4 microstates: LL, RR, LR, RL.

How about 3 molecules? Now we have: LLL, (LLR, LRL, RLL), (LRR, RLR, RRL), RRR (all L) (2 L, 1 R) (2 R, 1 L) (all R)

i.e. 8 microstates, 4 macrostates

How about 4 molecules? Now there are 16 microstates and 5 macrostates

(all L) (3L, 1R) (2L, 2R) (1L, 3R) (all R) (all L) (3L, 1R) (2L, 2R) (1L, 3R) (all R) (all In general:

	Ν	W	Μ
1 1	1	2	2
1 2 1	2	4	3
1 3 3 1	3	8	4
1 4 6 4 1	4	16	5
1 5 10 10 5 1	5	32	6
1 6 15 20 15 6 1	6	64	7
1 7 21 35 35 21 7 1	7	128	8
1 8 28 56 70 56 28 8 1	8	256 1	9 ▲
		2 ^N	N+1

This table was generated using the formula for # of permutations for picking n items from N total:

$$W_{N,n} = \frac{N!}{N! (N-n)!}$$
 i.e. $W_{6,2} = \frac{6!}{2! 4!} = 15$
"multiplicity"

Fundamental Assumption of Statistical <u>Mechanics</u>: All microstates are equally probable.

Thus, we can calculate the likelihood of finding a given arrangement of molecules in the container.

E.g. for 10 molecules:

Conclusion: Events such as the spontaneous compression of a gas (or spontaneous conduction of heat from a cold body to a hot body) are not impossible, but they are so improbable that they never occur.

"Improbable", quantitatively:

For large N, $\sigma/\mu \rightarrow 1/JN$

For N ~ NA, $\sigma/\mu \rightarrow 1.3 \times 10^{-12}$

~ 70% of time within 10⁻¹⁰ % of expected

Probability of < 10⁻⁹⁹ to find more than 2.7 x 10⁻⁹ % from expected! We can relate the **# of microstates** W of a system to its entropy S by considering the probability of a gas to spontaneously compress itself into a smaller volume.

If the original volume is V_i , then the probability of finding N molecules in a smaller volume V_f is

Probability = $W_f/W_i = (V_f/V_i)^N$

 $\ln(W_{f}/W_{i}) = N \ln(V_{f}/V_{i}) = n N_{A} \ln(V_{f}/V_{i})$ (1)

We have seen for a free expansion that

$$\Delta S = n R \ln(V_f/V_i)$$

So, using (1) for $ln(V_f/V_i)$,

 $\Delta S = (R/N_A) \ln(W_f/W_i) = k_B \ln(W_f/W_i)$

or

$$S_f - S_i = k \ln(W_f) - k \ln(W_i)$$

Thus, we arrive at an equation, first deduced by Ludwig Boltzmann, relating the entropy of a system to the number of microstates:

$S = k \ln(W)$

He was so pleased with this relation that he asked for it to be engraved on his tombstone.